

ITScript Net® - Installing SQL CE & Cab Files

~~~~~

## Using SQL CE (Microsoft SQL Compact Edition) on your mobile Windows device

**This article pertains to ITScriptNet software version 3.0 to version 3.2d only.**

**(This does NOT apply to solution packs nor ITScriptNet Indago)**

For ITScriptNet-designed data collection programs which are set to use SQL CE on devices running mobile Windows, please download from our website:

### Microsoft SQL Server Compact 3.5 Service Pack 1 for mobile Windows:

[http://www.z-space.com/redist/SSCE35SP2\\_DeviceRuntime-ENU.msi](http://www.z-space.com/redist/SSCE35SP2_DeviceRuntime-ENU.msi)


**SAVE** the download, then double-click to install to your computer.

SQL Server Compact 3.5 for devices Windows Installer (msi) file contains the CAB files and the DLLs for installing SQL Server Compact 3.5 on the mobile Windows devices.

### SQL CE Cab files to use - and for which mobile Windows Operating Systems on the devices:

➡ C:\Program Files\Microsoft SQL Server Compact Edition\v3.5\Devices\wce500\armv4i

**COPY** the matching files for your mobile device's Windows OS:




(see page 2 – steps to loading device)

# ITScript Net® - Installing SQL CE & Cab Files

~~~~~

SQL CE Cab files – Loading the device

1. Make sure the mobile device is connected to the computer via Mobile Device Center.
2. On the computer:
 - a. Select the correct 3 Cab files for your device's Windows operating system from the MS SQL Server Compact Edition folder as shown above (Page 1).
 - b. Right click and copy the 3 cab files.
 - c. From your Mobile Device Center, under File Management, click on the Browse....
 - d. A Windows Explorer will view files on your device.
 - e. Find the **device's** mobile Windows TEMP folder or persistent storage folder (such as Flash Disk or Application folder).
 - f. **Paste** the 3 copied files into that folder (this is still from within the *computer's* Browse/Explorer view into the device's files, paste into the device's folder).



3. On the device:

- a. Using the stylus and **on the device**, navigate to the device's Temp or storage folder where you pasted the 3 cab files.
- b. Double-tap on *each cab file*, **one at a time**, and wait, let each one install on the device.
- c. NOTE: the installation is a bit slower than you would expect (because the device's processor is slower than a computer's), you must be patient, allow each one of the cab files to fully install before moving on to the next cab file, or exiting the process. You might think the installation process was completed (the device may seem to pause), but it's not, just let it continue until it's done.
- d. For each cab file on the device, if you see a window asking to confirm the destination, just click the OK and let the device install where it wants to.
- e. You should see a progress bar during each cab file's installation. When the progress bar disappears, the install will have completed.

